

Fingering Rules

Fifth finger keys in scales

Most of the following rules govern the choice of left and right-hand fingerings in scales and arpeggios, this being the most frequent cause for confusion. In both scales and arpeggios, bottom F and second register C should be fingered with the right-hand fingering wherever possible:




In the scales of C major, A minor, G major, C minor and the chromatic scale starting on C, second register B will, therefore, be fingered with the left hand while the right fifth finger holds down the right-hand C key:



E harmonic minor is the only scale in which this is not possible as C is followed by D[#] in the second register and must therefore be played with the left hand. Arpeggios in which C is followed by E^b also require C to be fingered with the left hand (C minor, A^b major and F minor, the diminished seventh starting on F[#]. Additionally, the arpeggio of F minor and the diminished seventh starting on F require a left-hand bottom F).

In D major, B minor, A major and F[#] minor second register B should be fingered with the right-hand and C[#] with the left:



© Plan Z Music 2015, this edition 2019. All rights reserved. Reproduction and distribution of this publication in any form or by any means without the prior, written consent of the publisher is prohibited.


Fifth finger keys in arpeggios

When crossing the break in arpeggios, including seventh arpeggios, the right-hand 5th finger keys should be chosen for B, C, C^{\ddagger} (and D^{\flat}) whenever possible.

This applies to:	This does not	apply to:
A major	B major	
A minor	C minor	
B ^b minor	E major	
B minor	Ab major	
C major	G [#] minor	
D ^b major	F ⁷	
C# minor	Ab ⁷	
E ^b major	B ⁷	
D# minor	Dþ	
E minor	Εþ ⁷	
F major	F ^{‡07}	
F minor		
F# major		
F [#] minor		
G major		
E ⁷		
F# ⁷		
G ⁷		
A ⁷		
C ⁷		
D ⁷ E ⁰⁷		
E F ^{o7}		
-		


Fifth finger in third register

Top D, E^b, E and F should be played with the A^b/E^b key (R5) open to assist tuning:



Chromatic fingerings for B and F#


In the chromatic scales the alternative fingerings should be used for bottom B, throat F $^{\sharp}$ and second register F#.




The alternative fingering for bottom register B should also be used in the scale of G^{\ddagger} minor. The alternative fingerings for F[#] should also be used in the scales of F[#] major, F[#] minor, B^b harmonic minor (Gb), Db major (Gb) and D# minor.


Break fingerings in scales


There are three main patterns of fingering for crossing the break in scales.






This pattern is applied in F major, D melodic minor (descending) B^{\flat} major, G minor, E^{\flat} major, C melodic minor (descending), A^{\flat} major, F minor, D^{\flat} major, B^{\flat} minor, E^{\flat} melodic minor (ascending), C^{\ddagger} melodic minor (ascending).






This pattern is applied in C major, A minor, G major, E melodic minor (descending), C minor.




This pattern is applied in D melodic minor (ascending), E melodic minor (ascending), D major, B minor, A major, F[#] minor, E major, C[#] melodic minor (descending), B major, G[#] minor, F[#] major, D[#] melodic minor (descending).

Three scales do not conform to any of the above break patterns.

- **D** harmonic minor: crosses the break from B^{\flat} to left-hand C^{\ddagger} .
- **E harmonic minor:** crosses the break from A to right-hand B, then to left-hand C so that D[#] can be played in the right hand.
- **C[#] harmonic minor:** crosses the break from A to right-hand B[#] and then to left-hand C[#].
- **D**[#] harmonic minor: crosses the break from A[#] to right-hand B and then to C^x.





*The speaker key is not pressed for bottom F \sharp

In scales you should always use the left-hand fingering In arpeggios you should always use the right-hand fingering

THERE ARE <u>NO</u> EXCEPTIONS TO THIS RULE!